

# Galaxy Workflow ' bowtie2-alignment-se-dataset-collection'

Step	Annotation
------	------------

Step 1: Input dataset collection	
----------------------------------	--

<b>Input Dataset Collection</b>	
---------------------------------	--

<i>select at runtime</i>	
--------------------------	--

Step 2: Input dataset	
-----------------------	--

<b>input</b>	
--------------	--

<i>select at runtime</i>	
--------------------------	--

Step 3: FASTQ Groomer	
-----------------------	--

<b>File to groom</b>	
----------------------	--

Output dataset 'output' from step 1	
-------------------------------------	--

<b>Input FASTQ quality scores type</b>	
--	--

Sanger & Illumina 1.8+	
------------------------	--

<b>Advanced Options</b>	
-------------------------	--

Hide Advanced Options	
-----------------------	--

Step 4: Bowtie2	
-----------------	--

<b>Is this single or paired library</b>	
---	--

Single-end	
------------	--

<b>FASTQ file</b>	
-------------------	--

Output dataset 'output_file' from step 3	
--	--

<b>Write unaligned reads (in fastq format) to separate file(s)</b>	
--	--

False	
-------	--

<b>Write aligned reads (in fastq format) to separate file(s)</b>	
--	--

False	
-------	--

<b>Will you select a reference genome from your history or use a built-in index?</b>	
--	--

Use a genome from the history and build index	
---	--

<b>Select reference genome</b>	
--------------------------------	--

Output dataset 'output' from step 2	
-------------------------------------	--

<b>Set read groups information?</b>	
-------------------------------------	--

Do not set	
------------	--

<b>Select analysis mode</b>	
-----------------------------	--

1: Default setting only	
-------------------------	--

<b>Do you want to use presets?</b>	
------------------------------------	--

No, just use defaults	
-----------------------	--

<b>Save the bowtie2 mapping statistics to the history</b>	
---	--

False	
-------	--

Step 5: Flagstat	
------------------	--

<b>BAM File to report statistics of</b>	
---	--

Output dataset 'output' from step 4